Kodak Graphic Communications Canada Company
3700 Gilmore Way
Burnaby, B.C., Canada
V5G 4M1
Tel: 1.604.451.2700
Fax: 1.604.437.9891

Request support: http://graphics.kodak.com
ecentral.creo.com

Internal: 734-00443A-EN Rev A
Release date: 15 March 2006

Procedure

Connecting to Mac OS X Using Windows Access, ftp or VNC

Connecting to Mac OS X using ftp

Perform the following procedure if you want to connect to Mac OS X via ftp:

1. Edit the **inetd.conf** file in /etc on the Mac, as follows:
   ```
   #sudo vi /etc/inetd.conf
   #Password: *******
   ```
2. Uncommnet the line:
   ```
   # ftp     stream  tcp     nowait  root    /usr/libexec/tcpd       ftpd –l
   ```
3. Save the **wq!** file
4. Reboot the computer.

The following appears:

```
ftp      stream  tcp    nowait  root    /usr/libexec/tcpd       ftpd -l
#login   stream  tcp    nowait  root    /usr/libexec/tcpd       rlogind
#nntp    stream  tcp    nowait  usenet  /usr/libexec/tcpd       nntpd
#ntalk   dgram   udp    wait    root    /usr/libexec/tcpd       ntalkd
#shell   stream  tcp    nowait  root    /usr/libexec/tcpd       rshd
#telnet  stream  tcp    nowait  root    /usr/libexec/tcpd       telnetd
#uucpd   stream  tcp    nowait  root    /usr/libexec/tcpd       uucpd
#comsat  dgram   udp    wait    root    /usr/libexec/tcpd       comsat
tftp     dgram   udp    wait    nobody  /usr/libexec/tcpd       tftpd /p
rivate/tftpboot
#bootps  dgram   udp    wait    root    /usr/libexec/tcpd       bootpd
```


From now on you can connect to a Mac OS X via ftp, using:

ftp://<login:password>@<ip-address>

Connecting to Mac OS X using Windows Access

Perform the following procedure to connect to Mac OS X using Windows Access:

1. Open the Sharing window and enable Windows sharing, as shown in the figure.




2. Click **Accounts** and enable the account you would like to share.
   You can now map the share.
   For example: \\10.1.70.100\frankconrad\Desktop\Windows_Share
   where Windows_Share is a folder created on the Mac desktop.

Connecting to Mac OS X using VNC


Perform the following procedure to connect to Mac OS X using VNC:

Note: There is no need to install any VNC software on the Macintosh since it is part of Mac OS X.

1. Open the Sharing window and enable **Apple Remote Desktop**, as shown in the figure.



2. Click **Access Privileges** to define the sharing settings, as shown in the figure.



3. On your Windows computer, open the VNC software and change the options to full color, otherwise the screen will be black.

About Kodak Graphic Communications Group (GCG)

The leading provider of graphic communications solutions worldwide, Kodak's Graphic Communications Group (GCG) offers image capture systems; professional color, copydot, and high-speed document scanning systems; inkjet printing and proofing systems; workflow and color management software; thermal imaging devices for film, plates, and proofs; high-quality proofing media, printing plates, and recording film; on-demand color and black-and-white printing systems; data storage products; and professional services. Creo joined the GCG in June 2005, when it became a wholly owned subsidiary of Kodak. With corporate headquarters located in Rochester, N.Y., Kodak (NYSE: EK) had sales of $13.5 billion in 2004 and is committed to a digitally oriented growth strategy.

© 2006 Kodak. The Creo product names mentioned in this document are trademarks or service marks of Creo Inc., a subsidiary of Kodak, and may be registered in certain jurisdictions. Other company and brand, product, and service names are for identification purposes only and may be trademarks or registered trademarks of their respective holders. Data subject to change without notice.